



Bisoños Usuarios de GNU/Linux de Mallorca y Alrededores | Bergantells Usuaris de GNU/Linux de Mallorca i Afegitons

VGA externa en un IBOOK - Cómo hacer funcionar las X LCD+CRT

(17033 lectures)

Per **Toni Posadillo**, [tonimps](http://www.runsolutions.com) (<http://www.runsolutions.com>)

Creado el 04/09/2003 15:12 modificado el 04/09/2003 15:39

*Por fin podemos utilizar el IBOOK para realizar presentaciones con el **Proyector** o conectar un **CRT**. Esta testado en un IBOOK II con la ATI Radeon M6, no lo he probado con la M7.*

Para empezar necesitamos instalar el paquete xserver-xfree86-dri-trunk , ya que sino tendreis problemas con el refresco y la aceleración, y que esta disponible en:

```
deb http://people.debian.org/~daenzer/dri-trunk-sid/ ./
deb-src http://people.debian.org/~daenzer/dri-trunk-sid/ ./
```

Una vez instalado debemos hacer unos retoques tanto en el kdmrc como en el xdm-config

1º Editamos el /etc/kde3/kdm/kdmrc y en la sección [X-*-Core] añadimos los siguiente

```
[X-*-Core]
AuthNameManager=MIT-MAGIC-COOKIE-1
```

2º en /etc/X11/xdm/xdm-config añadimos lo siguiente

```
DisplayManager*authorize: false
```

Ahora basta que hagas un copy paste del fichero XF86Config-4

```
## Configuración del XF86config para dar salida por el CRT y LCD en
## modo xinerama
```

```
##
Section "ServerFlags"
Option "BlankTime" "3"
Option "StandbyTime" "7"
Option "SuspendTime" "10"
Option "OffTime" "15"
EndSection
```

```
Section "Files"
# FontPath "unix:/7100" # local font server
# if the local font server has problems, we can fall back on these
FontPath "/usr/lib/X11/fonts/misc"
FontPath "/usr/lib/X11/fonts/cyrillic"
FontPath "/usr/lib/X11/fonts/100dpi:unscaled"
FontPath "/usr/lib/X11/fonts/75dpi:unscaled"
```



```
FontPath "/usr/lib/X11/fonts/Type1"
FontPath "/usr/lib/X11/fonts/TrueType"
FontPath "/usr/lib/X11/fonts/Speedo"
FontPath "/usr/lib/X11/fonts/100dpi"
FontPath "/usr/lib/X11/fonts/75dpi"
FontPath "/var/lib/defoma/x-ttcidfont-conf.d/dirs/TrueType"
EndSection
```

```
Section "Module"
Load "GLcore"
Load "bitmap"
Load "dbe"
Load "ddc"
Load "dri"
Load "extmod"
# Load "freetype"
Load "xtt"
Load "glx"
Load "int10"
Load "record"
Load "speedo"
Load "type1"
Load "vbe"
EndSection
```

```
Section "InputDevice"
Identifier "Laptop Keyboard"
Driver "keyboard"
Option "CoreKeyboard"
Option "XkbRules" "xfree86"
Option "XkbModel" "macintosh"
Option "XkbLayout" "es"
EndSection
```

```
Section "InputDevice"
Identifier "Configured Mouse"
Driver "mouse"
Option "CorePointer"
Option "Device" "/dev/input/mice"
Option "Protocol" "ImPS/2"
Option "Emulate3Buttons" "true"
Option "ZAxisMapping" "4 5"
EndSection
```

```
Section "Device"
Identifier "ATI M6 Alone"
Driver "ati"
Option "AGPMode" "1"
Option "UseFBDev" "true"
VendorName "ATI"
BoardName "Radeon Mobility M6 LY"
BusID "PCI:0:16:0"
EndSection
```

```
Section "Device"
Identifier "ATI M6 Cloning"
Driver "ati"
Option "AGPMode" "1"
Option "UseFBDev" "true"
```



```
Option "MonitorLayout" "LVDS,CRT"
Option "CloneHSync" "30.0-100.0"
Option "CloneVRefresh" "50.0-160.0"
Option "OverlayOnCRT2"
VendorName "ATI"
BoardName "Radeon Mobility M6 LY"
BusID "PCI:0:16:0"
Screen 0
EndSection
```

```
Section "Device"
Identifier "ATI M6 Internal"
Driver "ati"
Option "AGPMode" "1"
Option "UseFBDev" "true"
Option "MonitorLayout" "LVDS,CRT"
VendorName "ATI"
BoardName "Radeon Mobility M6 LY"
BusID "PCI:0:16:0"
Screen 0
EndSection
```

```
Section "Device"
Identifier "ATI M6 External"
Driver "ati"
Option "AGPMode" "1"
Option "UseFBDev" "false" ##### ¡ojo! Framebuffers false para el externo
Option "MonitorLayout" "LVDS,CRT"
VendorName "ATI"
BoardName "Radeon Mobility M6 LY"
BusID "PCI:0:16:0"
Screen 1
EndSection
```

```
Section "Monitor"
Identifier "IDFP"
HorizSync 30-100
VertRefresh 50-160
Option "DPMS"
```

```
Mode "1024x768"
# D: 65.003 MHz, H: 48.365 kHz, V: 60.006 Hz
DotClock 65.004
HTimings 1024 1048 1184 1344
VTimings 768 771 777 806
Flags "-HSync" "-VSync" # atención: XFree86 no soporta aceleración
EndMode
EndSection
```

```
Section "Monitor"
Identifier "CRT"
HorizSync 30-100
VertRefresh 50-160
Option "DPMS"
```

```
Mode "1024x768"
# D: 65.003 MHz, H: 48.365 kHz, V: 60.006 Hz
DotClock 65.004
HTimings 1024 1048 1184 1344
```



```
VTimings 768 771 777 806
Flags "-HSync" "-VSync" # atención: XFree86 no soporta aceleración
EndMode
```

```
Mode "1280x1024"
# D: 134.21 MHz, H: ??? kHz, V: 73 Hz
DotClock 134.21
HTimings 1280 1336 1616 1728
VTimings 1024 1026 1038 1064
Flags "-HSync" "-VSync" # atención: XFree86 no soporta aceleración
EndMode
EndSection
```

```
Section "Screen"
Identifier "Screen Alone On DFP"
Device "ATI M6 Alone"
Monitor "IDFP"
DefaultDepth 24
SubSection "Display"
Depth 24
Modes "1024x768" "800x600" "640x480"
Virtual 1024 768
EndSubSection
EndSection
```

```
Section "Screen"
Identifier "Screen On DFP"
Device "ATI M6 Internal"
Monitor "IDFP"
DefaultDepth 24
SubSection "Display"
Depth 24
Modes "1024x768" "800x600" "640x480"
Virtual 1024 768
EndSubSection
EndSection
```

```
Section "Screen"
Identifier "Screen On CRT"
Device "ATI M6 External"
Monitor "CRT"
DefaultDepth 24
SubSection "Display"
Depth 24
Modes "1024x768" "800x600" "640x480"
Virtual 1024 768
EndSubSection
EndSection
```

```
Section "Screen"
Identifier "Screen On CRT 1024x768"
Device "ATI M6 External"
Monitor "CRT"
DefaultDepth 24
SubSection "Display"
Depth 24
Modes "1024x768" "800x600" "640x480"
Virtual 1024 768
EndSubSection
```



```

EndSection

Section "ServerLayout"
Identifier "Dual 1024x768"
Screen "Screen On DFP"
Screen "Screen On CRT 1024x768" LeftOf "Screen On DFP"
InputDevice "Laptop Keyboard"
InputDevice "Configured Mouse"
EndSection

```

```

Section "ServerLayout"
Identifier "Dual"
Screen "Screen On DFP"
Screen "Screen On CRT" LeftOf "Screen On DFP"
InputDevice "Laptop Keyboard"
InputDevice "Configured Mouse"
EndSection

```

```

Section "ServerLayout"
Identifier "Single"
Screen "Screen Alone On DFP"
InputDevice "Laptop Keyboard"
InputDevice "Configured Mouse"
EndSection

```

```

Section "ServerLayout"
Identifier "Cloned"
Screen "Screen Alone On DFP"
InputDevice "Laptop Keyboard"
InputDevice "Configured Mouse"
EndSection

```

```

Section "DRI"
Mode 0666
EndSection

```

#####

y eso es todo amigos, bueno si quereis afinar un poco más los modelines podeis ir a la siguiente dirección:

<http://koala.ilog.fr/cgi-bin/nph-colas-modelines>

E-mail del autor: toni_ARROBA_posadillo.com
Podrás encontrar este artículo e información adicional en: <http://bulma.net/body.phtml?nIdNoticia=1866>